

Install
just copy the .dll file into your
VST folder.

cytoSonic SPACE 360°

QUICK START GUIDE

Mouse Behavior
left: click to select, drag to adjust.
right: click to reset to default value.

Dimension Handle:
drag to change the
dimensions of the room.

Speakers:
drag L/R speakers to
change set their position
in the room.

Listener:
drag to change the
listener's position in the
room.

Room Scale:
adjust the size of the
room.

Levels:

Use the knobs to set the
relative levels of the
wavefront (DIRECT), early
reflections (REFLECT), and
reverb (AMBIENCE).

Edit Select:

Click on the knob labels to
open the respective
editing window for each
of the three elements of
the effect.

Editing Window:


Fine-tune the effect here.
(see below)

Info

Engage/Bypass

Preset Load/Save


Saved in .csp file extension. Use to copy room
signature to other instances of the plugin.




Pattern: Adjust the polar pattern of
the listener. Pattern ranges from omni
to hyper-cardioid.

Focus: Adjust the width of the stereo
field from 180° to 0°.

Spread: Adjust the lateral offset of the
two "ears".



Adjust the damping for each of the
walls of the virtual room. These
settings "cascade" down into the
AMBIENCE section.



Diffusion: Adjust the character of the
allpass response of the reverb.

Smear: Adjust the modulation depth
of the reverb's comb filters.

Lo-Cut: Remove low frequencies from
the reverb tail.

